


DFN SESSIES MET GEBRUIK VAN FSNAV-PLANS

Dit is geen uitgebreide handleiding maar een korte toelichting met screenshots om de beginners op weg te helpen.....


Bij sommige sessie-aankondigingen vind je in de sessie-kalender een navigatieplan met als extentie <.fsn>

Stop dat in de map <Plans> binnen <FSNavigator>


Activeer FSNav:



Als FSNav actief is kun je dat navplan als volgt oproepen:



Je ziet dan vanzelf het lijntje van de route verschijnen:



Je kunt hier (FMS) zorgen dat je autopilot alles afhandelt:

Id:

Plan

Edit

Options

Help

Id	Location	Freq	Course	IAS	VSpeed	Altitude	Distance	ETE	Fuel [Lb]
5	Lelystad - Rwy					0	0.0	00 00' 00"	0.0
Fix01	N52°28.06', E005°32.43'		51	161	1000	517	1.4	00 00' 31"	14.8
Fix02	N52°27.82', E005°32.88'		134	161	1000	651	0.4	00 00' 08"	3.8
Fix03	N52°26.81', E005°31.90'		213	162	1000	1079	1.2	00 00' 25"	12.3
LLS	LLS	326.0	3				1.0		

CDM1: 127.30

NAV1: 110.50

NAV2: 113.90

ADF: 0414.0

Transp.: 1200

318 deg

0 ft

0 ft/min

90 kts

AP Fly FP

HDG 360

ALT 00000

VS 00000

IAS 000

MACH 0.00

NAV1 000

APR BC

NAV2

Map

Plan

FMS

Fly Flightplan

Next

Prev

Fly Holding

M1	11:24:04	Aircraft		
M2	remaining:	136.9 nm	01 29' 17"	
Lelystad - Rwy				
LT	11:24:45	Rwy	5	
	176°	1.1 nm	00 00' 41"	
	remaining:	135.9 nm	01 28' 36"	
N52°28.06', E005°32.43'				
	11:25:40	Fix	Fix01	
	51°	2.5 nm	00 01' 36"	
	remaining:	134.5 nm	01 27' 41"	
N52°27.82', E005°32.88'				
	11:25:54	Fix	Fix02	
	134°	2.8 nm	00 01' 50"	
	remaining:	134.1 nm	01 27' 27"	
	12:53:21	Arrival		

N52 43.34 E004 10.20 = N52 43 21 E004 10 12

ehle eddl.fsn

Fokker F-50


Als je op <Plan> klikt zie je de details:

The screenshot displays a flight planning application. The top toolbar contains various icons for file operations, editing, and navigation. Below the toolbar, the main window is divided into several sections:

- Left Sidebar:** Contains flight parameters such as COM1 (127.30), NAV1 (110.50), NAV2 (113.90), ADF (0414.0), Transp. (1200), and various speed/altitude settings (318 deg, 0 ft, 0 ft/min, 95 kts, AP, Fly FP, HDG 360, ALT 00000, VS 00000, IAS 000, MACH 0.00, NAV1 000, APR BC, NAV2).
- Top Table:** A summary table of the flight plan with columns: Id, Location, Freq, Course, IAS, VSpeed, Altitude, Distance, ETE, and Fuel. It lists the main route (Lelystad - Rwy) and several fix points (Fix01, Fix02, Fix03) and a localizer (LLS).
- Central Map Area:** A large rectangular area for the map, currently showing a list of waypoints and their coordinates. The list includes Lelystad - Rwy, several fix points, LLS, and various other waypoints like FOXTD, BOT, VALSU, and Dusseldorf - ILS/GS: IDNE.
- Right Sidebar:** Titled "Airports with SID/STARs", it lists various regions and their associated airport counts: North America -- 252, Central America -- 7, Caribbean -- 18, South America -- 124, Europe -- 398, Middle East -- 23, Africa -- 37, Asia -- 215, and Oceania -- 38.
- Bottom Status Bar:** Displays the text "NYKER Departure EHLE", the file name "ehle eddl.fsn", and the aircraft type "Fokker F-50".

To zoom in, press right mouse button and move the mouse

Van tijd tot tijd moet je de SID/STARs-download uitvoeren voor de updates:



Helaas werkt dat niet meer omdat fsnavigator niet meer wordt onderhouden.